

Kali Linux ZH_TW



```
(kali@kali)-[~]
└─$ neofetch

kali@kali
OS: Kali GNU/Linux Rolling x86_64
Host: VMware Virtual Platform None
Kernel: 6.8.11-amd64
Uptime: 15 mins
Packages: 2783 (dpkg)
Shell: zsh 5.9
Resolution: 1632x920
DE: Xfce 4.18
WM: Xfwm4
WM Theme: Kali-Dark
Theme: Kali-Dark [GTK2], adw-gtk3-dark [GTK3]
Icons: Flat-Remix-Blue-Dark [GTK2/3]
Terminal: qterminal
Terminal Font: FiraCode 10
CPU: AMD Ryzen 9 6900HX with Radeon Graphics (4) @ 3.293GHz
GPU: 00:0f.0 VMware SVGA II Adapter
Memory: 627MiB / 3913MiB
```



ISO VM Kali Linux


```
sudo timedatectl set-timezone Asia/Taipei
timedatectl
```

```
kali@kali: ~
File Actions Edit View Help
(kali@kali)-[~]
└─$ sudo timedatectl set-timezone Asia/Taipei
[sudo] password for kali:
(kali@kali)-[~]
└─$ timedatectl
          Local time: Tue 2024-07-02 17:19:43 CST
          Universal time: Tue 2024-07-02 09:19:43 UTC
          RTC time: Tue 2024-07-02 09:19:43
          Time zone: Asia/Taipei (CST, +0800)
System clock synchronized: yes
          NTP service: inactive
          RTC in local TZ: no
(kali@kali)-[~]
└─$
```



```
sudo dpkg-reconfigure locales
```

```
["zh_TW.UTF-8"] <ok>
```



☐☐☐☐ "zh_TW.UTF-8"




```
(kali@kali)-[~]
└─$ sudo apt-get install fcitx5 fcitx5-chewing im-config zenity -y
正在讀取套件清單 ... 完成
正在重建相依關係 ... 完成
正在讀取狀態資料 ... 完成
下列的額外套件將被安裝：
fcitx5-config-qt fcitx5-data fcitx5-frontend-all fcitx5-frontend-gtk3 fcitx5-frontend-gtk4 fcitx5-frontend-qt5
fcitx5-frontend-qt6 fcitx5-modules libadwaita-1-0 libappstream5 libchewing3 libchewing3-data libfcitx5-qt-data libfcitx5-qt1
libfcitx5-qt6-1 libfcitx5config6 libfcitx5core7 libfcitx5gclient2 libfcitx5utils2 libime-bin libime-data
libime-data-language-model libimecore0 libimepinyin0 libimetable0 libkf5itemviews-data libkf5itemviews5 libkf5widgetsaddons-data
libkf5widgetsaddons5 libstemmer0d libxcb-ewmh2 libxcb-imdkit1 libxmlb2 zenity-common
建議套件：
fcitx5-chinese-addons kde-config-fcitx5 fcitx5-frontend-fbterm fcitx5-frontend-gtk2 fcitx5-frontend-tmux
下列【新】套件將會被安裝：
fcitx5 fcitx5-chewing fcitx5-config-qt fcitx5-data fcitx5-frontend-all fcitx5-frontend-gtk3 fcitx5-frontend-gtk4
fcitx5-frontend-qt5 fcitx5-frontend-qt6 fcitx5-modules im-config libadwaita-1-0 libappstream5 libchewing3 libchewing3-data
libfcitx5-qt-data libfcitx5-qt1 libfcitx5-qt6-1 libfcitx5config6 libfcitx5core7 libfcitx5gclient2 libfcitx5utils2 libime-bin
libime-data libime-data-language-model libimecore0 libimepinyin0 libimetable0 libkf5itemviews-data libkf5itemviews5
libkf5widgetsaddons-data libkf5widgetsaddons5 libstemmer0d libxcb-ewmh2 libxcb-imdkit1 libxmlb2 zenity zenity-common
升級 0 個，新安裝 38 個，移除 0 個，有 0 個未被升級。
需要下載 0 B/51.4 MB 的套件檔。
此操作完成之後，會多佔用 98.0 MB 的磁碟空間。
```

im-config

im-config

輸入法設定程式 (im-config, 版本 0.57-2)

Current configuration for the input method:

- * Default mode defined in /etc/default/im-config: 'auto'
- * Active configuration: 'missing' (normally missing)
- * Normal automatic choice: 'fcitx5' (normally ibus or fcitx5)
- * Override rule: 'zh_CN,fcitx5:zh_TW,fcitx5:zh_HK,fcitx5:zh_SG,fcitx5'
- * Current override choice: 'fcitx5' (Locale='zh_TW')
- * Current automatic choice: 'fcitx5'
- * Number of valid choices: 1 (normally 1)
- * Desktop environment: 'XFCE'

The configuration set by im-config is activated by re-starting the system.

如果正在使用的是 default/auto/cjkv/missing，您不需要另外選擇即可使用自動設定。

取消(C)

確定(O)

""

輸入法設定程式 (im-config, 版本 0.57-2)



您要指定使用者設定值嗎？

* 如果您不想要指定，請選擇「否」。(建議)

* 如果您想要指定，請選擇「是」。

否(N)

是(Y)

fcitx5

輸入法設定程式 (im-config, 版本 0.57-2)

Select 使用者設定值. The user configuration supersedes the system one.

選擇	名稱	註釋
<input type="radio"/>	auto	activate im with @-mark in its description
<input type="radio"/>	ckv	use auto mode based on locale and desktop
<input type="radio"/>	REMOVE	移除使用者設定值 /home/kali/.xinputrc
<input checked="" type="radio"/>	fcitx5	activate Flexible Input Method Framework v5 (fcitx5) @!
<input type="radio"/>	none	do not activate any IM from im-config and use desktop default

取消(C)

確定(O)

im-config



Updated 2 July 2024 10:08:51 by []